

Creating New Neuron Models for SpiNNaker

Introduction

This manual will guide you in the creation of new neuron models to be run on SpiNNaker. This includes the C code that will be compiled to run on the SpiNNaker hardware, as well as the Python code which interacts with the PyNN script to configure the model.

Installation


In order to create new models, you will need to ensure that you have set up a development environment suitable for compiling C code for SpiNNaker. This can be done by following the instructions here:

<http://spinnakermanchester.github.io/2016.001.AnotherFineProductFromTheNonsenseFactory/spynaker/PyNNOnSpiNNakerExtensions.html>


Project Layout

The recommended layout for a new model project is shown below; this example shows a model called “my_model”, with current-based exponential synapses. It is recommended that the C and Python code is kept in the same project to help keep them synchronized.

C code



Python code



This template structure can be downloaded from one of the following locations:

<https://github.com/SpiNNakerManchester/SpyNNakerNewModelTemplate/archive/2016.001.zip>

<https://github.com/SpiNNakerManchester/SpyNNakerNewModelTemplate/archive/2016.001.tar.gz>

C model builds

All neuron builds consist of a collection of components which when connected together produce a complete neural model. These components are defined in **Table 1**.

Component	Definition
Input component	The type of input the model takes. Currently there are conductance and current based inputs supported by sPyNNaker. It is possible to define other input types, but this is not described in this tutorial.
Synapse type component	The synapse type controls the shaping of the synapses in response to the input weights. Within sPyNNaker, support so far includes exponential synapses (with one excitatory and one inhibitory synapse per neuron which decay exponentially with a configured time-constant) and dual-excitatory exponential synapses (with 2 separate excitatory synapses and one inhibitory synapse per neuron, decaying as per the previous type).
Threshold component	Determines the threshold of the membrane voltage which determines when the neuron spikes. Currently the only implementation is a static threshold.
Additional input component	Any additional input current that might be based on the membrane voltage or other parameters. This is currently only implemented in the SpyNNakerExtraModelsPlugin.
Neuron model component	Determines how the neuron state changes over time and the outputs the current membrane voltage of the neuron. Currently there are IZK and LIF implementations supported by sPyNNaker.
Synapse dynamics component	Determines how plasticity works within the model. sPyNNaker implements a model for no plasticity (i.e. static dynamics), and two different STDP dynamics models. Only static dynamics are considered in this tutorial.

Table 1: Different supported components

Each build is stored within its own folder in the `c_models->src->neuron->builds` directory. Within each build is a `c Makefile` which describes the separate components required to build that specific form of Neuron model.

If we look at the simple `my_model_curr_exp`'s makefile located in:

`c_models->src->neuron->builds->my_model_curr_exp->Makefile`

we can see the lines show in **Code 1**.

```
1. APP = $(notdir $(CURDIR))
2. BUILD_DIR = build/
3.
4. NEURON_MODEL = $(EXTRA_SRC_DIR)/neuron/models/my_neuron_model_impl.c
5. NEURON_MODEL_H = $(EXTRA_SRC_DIR)/neuron/models/my_neuron_model_impl.h
6. INPUT_TYPE_H = $(SOURCE_DIR)/neuron/input_types/input_type_current.h
7. THRESHOLD_TYPE_H = $(SOURCE_DIR)/neuron/threshold_types/threshold_type_static.h
8. SYNAPSE_TYPE_H = $(SOURCE_DIR)/neuron/synapse_types/synapse_types_exponential_impl.h
9. SYNAPSE_DYNAMICS = $(SOURCE_DIR)/neuron/plasticity/synapse_dynamics_static_impl.c
10.
11. include ../Makefile.common
```

Code 1: my_model_curr_exp's Makefile

- Line 1 declares the name of the APP - here we are using the name of the current directory. The aplx extension is added automatically.
- Line 2 declares the directory in which the model will be built. This is where object files and other intermediate files are stored; the final aplx location is determined in Makefile.common (see later).
- Lines 4 and 5 states the files that make up the neuron model component (described in **Table 1**) used for this model build (both the .c and .h files are needed). Note that these are stated to be in the \$(EXTRA_SRC_DIR) folder - this is declared to be the c_models/src folder within the archive within Makefile.common. The sPyNNaker standard source files are declared to be within \$(SOURCE_DIR), and these are used by other components.
- Line 6 states the input type component (described in **Table 1**) for this model. Input types are implemented entirely in a header file.
- Line 7 states the threshold type component (described in **Table 1**) for this model. Threshold types are implemented entirely in a header file.
- Line 8 states the synapse type component (described in **Table 1**) for this model. Synapse types are implemented entirely in a header file.
- Line 9 states the synapse dynamics component (described in **Table 1**) for this model.
- Line 11 tells the make system to import the next level up Makefile so that it can detect where the rest of the code needed to be linked in can be found.

Other Makefile instances might also include TIMING_DEPENDENCE_H and WEIGHT_DEPENDENCE_H; these are used when the synapse dynamics includes plasticity. A tutorial on how to add new plasticity is covered [here](#).

To make a new Neuron model build, you must either:

1. Create a copy of the example builds discussed above,
2. Modify the names and component listings,
3. Modify Line 1 of the Makefile located in src->neuron->Makefile so that it includes your new build.

Or:

1. Change the template's component listings directly.

Compiling a new model

Once the Makefile has been created, you can build the binary by simply changing to the directory containing the Makefile and typing:

```
make
```

As the build relies on header files that are not explicitly specified in the Makefile, some of the changes that you make may require you to clean the build before building it, by running

```
make clean
```

Finally, you can also build the application in debug mode by typing:

```
make DEBUG=DEBUG
```

This will enable the log_debug statements in the code, which print out information to the iobuf buffers on the SpiNNaker machine; to read this there is a simple application in the example folder that can read iobuf buffers, which can be invoked as follows:

```
python iobuf.py <machine_name> <app_name>
```

where <machine_name> is the hostname or IP address of the SpiNNaker board, and <app_name> is the name of application (without the .apl extension). This will retrieve the iobuf buffers for every instance of the application that is found to be running.

C code file interfaces

The rest of this section goes through the different components interfaces and tries to explain what each one does, for the case where you need to create a new component for your neuron build.

Neuron Models

The C header file defines:

- The neuron data structure `neuron_t`. This includes the parameters and state for each neuron to be executed on a core. This commonly includes the membrane voltage of the neuron, as well as an offset input current.
- The global parameters data structure `global_neuron_params_t`. This includes parameters that are shared across all neurons within a population. This might include such things as the time step of the simulation.

See `neuron_model_my_model_curr_exp.h` in the template for an example of a header file. Comments show where the file should be updated to create your own model.

The C code file defines the functions that make up the interface of the neuron API. Note that pointer types are automatically created for the data structures defined in the header as follows:

```
neuron_t * → neuron_pointer_t
global_neuron_params_t * → global_neuron_params_pointer_t
```

- `void neuron_model_set_global_neuron_params(global_neuron_params_pointer_t params)`
This function is used to set the global parameters after they have been read by the initialization function. This would often be used to store the parameters in a static variable for later use.
- `state_t neuron_model_state_update(input_t exc_input, input_t inh_input, input_t external_bias, neuron_pointer_t neuron)`
This function takes the excitatory and inhibitory input; any external bias input (used in some plasticity models); and a neuron data structure; and uses these to compute the new state of the given neuron at this timestep. This function is where any differential equation solving should be implemented. After the state update, the function should return the value of the membrane voltage. Note that the input will always be presented as current - conductance input is converted to current input in the input type. Additionally, the input values are all positive, including the inhibitory input; thus if the total input current is being considered, the inhibitory input current should be subtracted from the excitatory input current.
- `state_t neuron_model_get_membrane_voltage(neuron_pointer_t neuron)`
This function should return the membrane voltage of the neuron from the given neuron structure. This may simply return the value of a variable in the structure, or it might perform a more complex calculation to obtain the membrane voltage. The value returned is used for the recording of the membrane voltage in the simulation, and is taken before the state update is performed.
- `void neuron_model_has_spiked(neuron_pointer_t neuron);`

This function is used to reset neuron parameters after it has spiked. It is called only if the membrane voltage value returned from `neuron_model_state_update` is determined to be above the threshold determined by the threshold type.

- `void neuron_model_print_parameters(restrict neuron_pointer_t neuron)`
This function is only used when the neuron model is compiled in “debug” mode. It should use the “log_debug” function to print each of the parameters of the neuron that don’t change during the run, and that might be useful in debugging.
- `void neuron_model_print_state_variables(restrict neuron_pointer_t neuron)`
This function is only used when the neuron model is compiled in “debug” mode. It should use the “log_debug” function to print each of the state variables of the neuron that change during a run and that might be useful in debugging.

See `neuron_model_my_impl.c` in the template for an example of an implementation of the neuron interface.

A number of other modules are available for use for performing mathematical functions as part of the neuron state update. The `spinn_common` library provides a number of efficient fixed-point implementations of common functions. This includes `random.h`, which provides random number generation, `normal.h`, which provides normal distributions, `exp.h`, which provides an exp function and `log.h` which provides a log function.

Synapse types

The synapse type header file defines the `synapse_param_t` data structure that determines the parameters required for shaping the synaptic input. For example, this might be done to compensate for the valve behaviour of a synapse in biology (spike goes in, synapse opens, then closes slowly). The parameters for all the synaptic inputs for a single neuron need to be defined in this structure; for example, if there are different parameters for excitatory and inhibitory neurons, both of these parameters must be explicitly defined in this structure. The structure might also contain parameters for computing the initial value that will be added to the input buffer following a spike from a preceding neuron.

Note that the input will have already been delayed by the appropriate amount before it reaches this function, and that the input weights from several spikes may be combined into a single weight. Additionally, the input weights might be either current or conductance as determined by the input type. The synapse type should not perform any conversion of the weights.

The synapse type header file also defines the functions that make up the interface of the synapse type API. The synapse Type API requires the following interface functions to be implemented.

- `static void synapse_types_shape_input(
input_t *input_buffers, index_t neuron_index,
synapse_param_t* parameters);`

Shapes the values (current or conductance) in the input buffers for the synapses of a given neuron. The input buffers for all neurons and synapse types are given here, and the following function can be used to obtain the index of the appropriate input buffer given the indices of the neuron and of the synapse (e.g. if there is an excitatory and inhibitory synapse per neuron, the indices might be 0 and 1 respectively):

```
index_t synapse_types_get_input_buffer_index(synapse_index,  
neuron_index)
```

- `static void synapse_types_add_neuron_input(
input_t *input_buffers, index_t synapse_type_index, index_t
neuron_index,
synapse_param_t* parameters, input_t input)`

Adds a synaptic weight input to the input buffer for a given synapse of a given neuron after a spike has been received (and appropriately delayed). This allows the weight to be scaled as required before it is added to the buffer.

- `static input_t synapse_types_get_excitatory_input(input_t *input_buffers, index_t neuron_index)`
Returns the total combined excitatory input from the buffers available for a given neuron id. Note that if several synapses are excitatory, this function should add up the input values (or perform an otherwise appropriate function) to return the total excitatory input value.
- `static input_t synapse_types_get_inhibitory_input(input_t *input_buffers, index_t neuron_index)`
Extracts the total combined inhibitory input from the buffers available for a given neuron id. Note that if several synapses are inhibitory, this function should add up the input values (or perform an otherwise appropriate function) to return the total inhibitory input value. Note also that the value should be a positive number; subtraction is performed in the neuron model as required.
- `static const char *synapse_types_get_type_char(index_t synapse_type_index)`
Returns a human readable character for the type of synapse. Examples would be X = excitatory types and I = inhibitory types.
- `static void synapse_types_print_parameters(synapse_param_t *parameters)`
Prints the static parameters of the synapse type. This is currently only executed when the models are in debug mode.
- `static void synapse_types_print_input(input_t input_buffers, index_t neuron_index)`
Prints the input for a neuron id given the available inputs. This is currently only executed when the models are in debug mode.

See `synapse_types_my_impl.h` for an example of an implementation of a synapse type.

Threshold types

The threshold type header file defines the `threshold_type_t` data structure that declares the parameters required for the threshold type. This might commonly include the actual threshold value amongst other parameters. The header also defines the functions that make up the interface of the threshold type API. The threshold Type API requires the following interface functions to be implemented.

- `static bool threshold_type_is_above_threshold(state_t value, threshold_type_pointer_t threshold_type)`
Determines if the threshold has been reached; if the neuron is to spike, given the value of the state variable, true is returned, otherwise false is returned.

Set `my_threshold_type.h` for an example of an implementation of a threshold type.

Additional inputs

The additional input header file defines the `additional_input_t` data structure, which declares the parameters required for the additional input. The header also defines the functions that make up the interface of the additional input type API. The additional input Type API requires the following interface functions to be implemented:

- `static input_t additional_input_get_input_value_as_current(additional_input_pointer_t additional_input, state_t membrane_voltage)`

Gets the value of current provided by the additional input. This may or may not be dependent on the membrane voltage.

- `static void additional_input_has_spiked(
 additional_input_pointer_t additional_input)`
Notifies the additional input type that the neuron has spiked.

Python Model Builds

Once the C code has been constructed, the PyNN model must be created in Python to translate the PyNN parameters into a form that the C code can understand. In PyNN, populations can be made up of an arbitrary number of neurons, however to maintain real-time operation the number of neurons that are simulated on each core must be limited. The PACMAN module is used by sPyNNaker to partition the populations into subpopulations, based on the specified maximum number of atoms per core of the model, as well as the resources required by the synaptic matrix. The DataSpecification module is then used to write the data for each subpopulation. This is then loaded onto the machine, along with binary executable, using SpiNNMan.

As with the C code, there are number of components that can be re-used, so that only properties relevant to the new model itself need to be defined. This is done by constructing an individual component for:

1. Neuron model,
2. Input type,
3. Synapse type,
4. Threshold type,
5. Additional input.

These 5 components are then handed over to the main interface object that every neuron model has to extend.

If we look at the `my_model_curr_exp` in `python_models -> neuron -> builds` directory, we will see the code shown in **Code 4** where the `my_model_curr_exp` builds its components and hands them over to the main sPyNNaker interface. The breakdown is as follows:

1. On Lines 91 and 92 the neuron model component is created.
2. On Lines 96 and 97 the synapse type component is created.
3. On Line 101 the input type component is created.
4. On Line 105 the threshold type component is created.
5. Line 109 shows that this model does not contain any additional input components.
6. Lines 113 to 135 show the handing over of these separate components to the sPyNNaker main system which will handle all the python support. Note that the binary must match the name of the `apl` file generated by the C code.

```
89.     # TODO: create your neuron model class (change if required)
90.     # create your neuron model class
91.     neuron_model = MyNeuronModel(
92.         n_neurons, machine_time_step, i_offset, my_parameter)
93.
94.     # TODO: create your synapse type model class (change if required)
95.     # create your synapse type model
96.     synapse_type = SynapseTypeExponential(
97.         n_neurons, machine_time_step, tau_syn_E, tau_syn_I)
98.
99.     # TODO: create your input type model class (change if required)
100.    # create your input type model
101.    input_type = InputTypeCurrent()
```

```

102.
103.  # TODO: create your threshold type model class (change if required)
104.  # create your threshold type model
105.  threshold_type = ThresholdTypeStatic(n_neurons, v_thresh)
106.
107.  # TODO: create your own additional inputs (change if required).
108.  # create your own additional inputs
109.  additional_input = None
110.
111.  # instantiate the sPyNNaker system by initializing
112.  # the AbstractPopulationVertex
113.  AbstractPopulationVertex.__init__(
114.
115.      # standard inputs, do not need to change.
116.      self, n_neurons=n_neurons, label=label,
117.      machine_time_step=machine_time_step,
118.      timescale_factor=timescale_factor,
119.      spikes_per_second=spikes_per_second,
120.      ring_buffer_sigma=ring_buffer_sigma,
121.      incoming_spike_buffer_size=incoming_spike_buffer_size,
122.
123.      # TODO: Ensure the correct class is used below
124.      max_atoms_per_core=MyModelCurrExp._model_based_max_atoms_per_core,
125.
126.      # These are the various model types
127.      neuron_model=neuron_model, input_type=input_type,
128.      synapse_type=synapse_type, threshold_type=threshold_type,
129.      additional_input=additional_input,
130.
131.      # TODO: Give the model a name (shown in reports)
132.      model_name="MyModelCurrExp",
133.
134.      # TODO: Set this to the matching binary name
135.      binary="my_model_curr_exp.aplx")

```

Code 4: Subsection of the my_model_curr_exp.py class

Take care to note that the same components are used in the python as are used in the c code's *Makefile*. This means for every new component you build for a neuron build in c which is not originally supported by the sPyNNaker tools, you need to build a corresponding python component file.

In the new_template folder there are a set of template files within the template directory for each python component. These are located under python_models -> neuron. These detail the parts of the class that need to be changed for your model.

Python __init__.py files

Most of the __init__.py files in the template do not contain any code. The one within python_models is the exception; this file adds the model_binaries module to the executable paths, allowing sPyNNaker to search this folder for your compiled binary. You can also import your module here to make it easy to use in other scripts.

Python setup.py file

This file enables you to install the new module. This is set up to install all the modules in the template; if you add any modules, these also need to be added to this file (it is not recursive; each module has to be

added separately). To add the module to your python environment in such a way that you can still edit it, you can run:

```
[sudo] python setup.py develop [--user]
```

You need to use `sudo` if you are installing centrally on Linux or Mac OS X; on windows you need to be in an Administrative console. Add `--user` instead if you want to install only for your username (you shouldn't mix these two options, or you will end up installing it only for the root user).

Using your module

In order to use the new module, you need to import your module in addition to PyNN e.g. for the template module, you can do the following:

```
import pyNN.spiNNaker as p
from python_models.neuron.builds.my_model_curr_exp import MyModelCurrExp
pop = p.Population(1, MyModelCurrExp, {})
```

A more detailed example is shown in the template in `examples/my_example.py`.